

# **Installation & Administration Guide**



#### © 2012 FileOnQ, Inc. All rights reserved.

This product is protected by United States Patent 7,599,942B1 and United States Patent 8,176,093 B2 The information contained in this document is subject to change without notice.

#### **About This Guide**

This guide shows you how to install and configure the FileOnQ Database and Desktop software. It is assumed that you are familiar with Microsoft SQL Server and the Windows operating system, as well as concepts related to computer networks and security. It is also assumed that Microsoft SQL Server is already running in your environment. For information on SQL Server installation and setup, see your SQL Server documentation.

The installation procedure consists of the following 10 steps.

Step 1: Verify Server and Client Requirements
Step 2: Install an OnQ Database on your Server5
Step 3: Install the FileOnQ Portal Administrator (New Installations Only)7
Step 4: Install OnQ Administrative Tools (New Installations Only)8
Step 5: Create an OnQ Application
Step 6: Enable Access to the OnQ Application11
Step 7: Request and Apply the License13
Step 8: Install OnQ Desktop Software15
Step 9: Install Peripheral Hardware to Use with FileOnQ16
Step 10: Install Optional Modules17

#### **Overview of the OnQ System**

The OnQ system is a 32-bit, Windows-compliant application that uses Microsoft SQL Server as its backend database. It is often used in conjunction with peripheral hardware such as barcode scanners. The OnQ system may include the following optional modules:

eDocs: Electronic documents stored in a SQL database repository.

**WebView:** A browser-based application that runs on Internet Explorer version 6.x and later. It is a .NET application that runs on an Internet Information Services (IIS) server.

**MobileOnQ:** An application that works in conjunction with Motorola's portable MCxx PDA to allow transactions from remote locations. The mobile device can use a wireless network or a 3G network. It runs by way of web services installed on your IIS server.

#### Step 1: Verify Server and Client Requirements

Before you begin the installation procedure, make sure that the server and all client machines meet the minimum system requirements.

For server requirements, see Server Hardware and Software Requirements.

For client requirements, see <u>Client Machine Requirements</u>.

## Step 2: Install an OnQ Database on your Server

These instructions assume that Microsoft SQL Server is already running in your environment. For information on SQL Server installation and setup, see your SQL Server documentation.

Two options are available for installing an OnQ database:

- Restore an existing OnQ database and install it on your SQL Server machine.
- Create a new, empty database.

# OPTION 1: Use the DBRestore utility to restore an existing OnQ database on your SQL Server machine

Use this option if FileOnQ technical support created your OnQ database and supplied a database backup file. You can also use this option if you want to copy your existing OnQ database as a starting place for deploying a new database, or if you are splitting your first database into two.

The DBRestore utility creates an SQL script and allows you to run the SQL statements directly from the utility. Alternatively, you can copy the SQL script and run it with SQL Server Management Studio to make modifications, such as changing the user name.

- 1. Move the backup file to the SQL Server machine. The file must physically reside on this server.
- Download the DBRestore utility (DBRestore.exe, 84.0 KB) from the following link: <u>https://www.onlinefilefolder.com/2sk8ZbNWK5I1aF</u>
- 3. Run DBRestore. The FileOnQ Restore window appears.

K FileOnQ Restore
IMPORTANT: This tool is designed to be run on the server. Please do not attempt to restore a database from a client desktop machine.
Database Name:
Backup file:
Connect
Data directory: C:\SQLData\
SQL Options
Replace existing database if exists     Update Statistics (Recommended)     Add login [fileonquser] to SQL Server
<u>×</u>
1
<u>ل</u>
× ×
<u>H</u> estore <b>Dose</b>

- 4. In the **Database Name** field, type a name for the new database.
- 5. Click the first ellipsis button to browse to the database backup file.
- Click the Connect button to establish a connection with the SQL Server. A login window appears. Supply the server name and the System Administrator (sa) login and password. Click OK.
- If you are running the DBRestore utility to replace an earlier installation of the OnQ

- SQL Options	
<ul> <li>Replace existing database if exists</li> <li>Add login (fileonquser) to SQL Server</li> </ul>	Update Statistics (Recommended)

database, select the **Replace existing database if exists** check box. Otherwise, keep the default settings.

8. Click **Restore**. Watch for messages that indicate a successful restoration. Click **Close**.

🍢 FileOnQ Restore		X
Restore Database : Succeeded Update Statistics : Succeeded Relink Database User : Succeeded		A 7
<		>
Ready!	<u>R</u> estore	<u>C</u> lose

#### OPTION 2: Create a blank OnQ database for a new project

Use this option to create a new, empty OnQ database. It will not contain any fields for user data. After you finish the installation procedure, use the OnQ Profiler to define all user fields.

The install files received from FileOnQ include an installation script that will build an empty OnQ database.

**NOTE** You must use an installation script that is compatible with the version of your database. Send an email message to <u>support@fileonq.com</u> to get the correct script to run on your server. Include the version of your OnQ Desktop software, which appears at the top of your login screen.



#### Step 3: Install the FileOnQ Portal Administrator (New Installations Only)

The installer file package from FileOnQ includes a SQL script to install the Portal Administrator on your SQL Server machine.

If you have previously installed an OnQ (version 6 or greater) database, the FileOnQ Portal Administrator is already installed on your SQL Server machine. This step is required only if this is the first OnQ database ever installed on your system, or if you are establishing another administrative entity for an OnQ database that will not be accessed by current OnQ users.

- 1. In the FileOnQ installer file package, find the SQL script for installing the Portal Administrator, and then run the script from SQL Server Management Studio.
- 2. Configure the access to this program: go to C:\Program Files\FileOnQ\FQPortalAdmin and open the FQPortalAdmin.exe.config file with a text editor.
- 3. Type the correct values for dbportalserver, dbportaldbname, dbportaldblogin, and dbportaldbpassword. Save and close the file.

```
<?xml version="1.0"?>
<configuration>
<appSettings>
<add key="dbportalserver" value="sqlserver2" />
<add key="dbportaldbname" value="fqportal" />
<add key="dbportaldblogin" value="fileonquser" />
<add key="dbportaldbpassword" value="passpass" />
<add key="dbportaldbpassword" value="passpass" />
<add key="APPWINAUTHCSTemplate" value="Data Source={0};:
<add key="APPSQLAUTHCSTemplate" value="Server={0};Initia
<add key="PORTALSQLCSTemplate" value="Server={0};Initia
<add key="PORTALSQLCSTemplate" value="Server={0};Initia
</appSettings>
<startup>
<startup>
</confiduration>
```

### Step 4: Install OnQ Administrative Tools (New Installations Only)

If you have previously installed an OnQ database, the administrative tools are already installed on a PC in your environment. This step is required only if this is the first OnQ database ever installed on your system, or if you are establishing another administrative entity for an OnQ database that will not be accessed by current OnQ users.

The installer file package from FileOnQ includes one installer (FQDesktopxx.msi). This file installs the Desktop Client and the administrative tools.

1.	Locate the .msi file from the FileOnQ installation files.	FQDesktop61.msi 61,279 KB Windows Installer P 6/1/2012 2:55 PM
2. Double-click the .msi file, click through the first few screens of the Setup wizard, and then select <b>Custom Setup</b> . For both		FileOnQ Desktop 6.1.3202 - InstallShield Wizard         Custom Setup         Select the program features you want installed.
the application and the administration tools, select <b>This feature, and all</b> <b>subfeatures, will be</b> <b>installed on local hard</b> <b>drive</b> . Do not use the default (with the red X in the window), which skips the administrative tools.	Click on an icon in the list below to change how a feature is installed.	
3.	Click <b>Next</b> through the rest of the installer windows, and use the defaults for the remaining settings.	X     This feature will not be available.       InstallShield

After the installation is complete, you should see a **New Programs Installed** message on your Windows Start menu. The FileOnQ folder will contain the Desktop, Administrator, and Profiler programs.

### Step 5: Create an OnQ Application

You use the Portal Administrator to create an OnQ application.

- 1. Click Start > FileonQ > FQPortalAdmin > FileonQ Portal Administrator. The Portal Administrator dialog box appears.
- Click the Create a new Application icon, located at the upper-left corner of the window. The Application dialog box appears.
- 3. Enter values into the following fields and click OK:
  - **Application Name**: Enter a unique name for the application.



- Select the **Active** check box. If you are licensed for and want to enable web browser access (WebView), select the **Enable Web Access** checkbox.
- If you want to use Active Directory to define and maintain security groups, select the **Use Active Directory for application authentication** checkbox.
- Server Address, Database Name: Enter the machine name of the server, and the name of the OnQ database that you created or restored in Step 2 on page 5.
- Login, Password: Enter login credentials.

🛃 Ap	plication
Application	Application Name :       Ledgers         Image: Active       Enable Web Access         Image: Use Active Directory for application authentication
SQL Server Database	Connection String Template : Server={0};Initial Catalog={1};User ID={2};Password={3}   Server Address : SQLServer2   Database Name : Onq_ledger     Authentication   Use Windows Authentication Mode   Login : fileonquser   Password :
	<u>O</u> K <u>C</u> ancel

💀 FileOnQ/E vide	🕵 FileOnQ/E videnceOnQ Portal Administrator 📃 💼 💌				
i 😂 🗟 🚳 🖏 🏷 🧀 🛹 💥 🕑					
Name	DB Server	Database	Active	Web Access Enabled	Active Directory Authentication
Evidence	SQLServer2	EvidenceDemo	×	<b>~</b>	
FileOnQ	SQLServer2	FileOnQDemo	\$	×	
Ledgers	SQLServer2	Onq_ledger	4	4	
•					•
					.:

The new application now appears on the **Portal Administration** dialog box.

## Step 6: Enable Access to the OnQ Application

When client Desktop users log into an OnQ application, the system reads a file called ServerProfiles.xml. This file identifies the location of the Portal Administrator, which maintains your site's OnQ application and the credentials required for users to access it.

If your organization uses more than one OnQ application, users indicate which application they want to log into by choosing it from the **Connection Profile** drop-down list on the **Login** window.

Your workstation's C:\Program Files\FileOnQ\FileOnQ <version> folder contains a default ServerProfiles.xml

file. You must edit it, by using the FileOnQ Server Profiles Administrator (Admin Tool), to point to the Portal Administrator.

- From the Windows Start menu, start the FileOnQ Administrator application. A login screen appears.
- Log in with fileonqadmin as your initial login. FileOnQ Support will provide your initial password. Click OK. The Admin Tool launches.

🖄 FileOnQ 6.1 S	erver P	rofiles Administral	tor		
<u>Eile P</u> rofile					
🗅 🗐 🌁		Current Location: C	:\Program Files\FileOnQ\File	OnQ 6.1\ServerProf	iles.×ml
Profile Name	Server	Name/Address	Database Name	Login ID	UseAD
					1.

 For a new installation, you should select a network location to store the ServerProfiles.xml file. To set the location, from the Admin Tool, select File > Change Location, and then specify the network location.

🝍 ServerProfiles path	×
Please enter the location (path) of the folder where the ServerProfiles.xml file is stored. If need help, please contact your System Administrator.	you
Important: You must be logged on to Windows with an account that is assigned the 'Local Administrator' role before you can successfully set the path.	
:\Program Files\FileOnQ\FileOnQ 6.1	
OK Cancel	

Connection Profile:	Evidence 🗾	
User ID:	Evidence Ledgers	5
Password:		

Admin Tool Login			
Login ID:	fileonqadmin		
Password:	***		

- 4. From the Admin Tool, select **File > Edit Portal** to edit the ServerProfiles.xml file. The **FileOnQ Portal Database** window appears. Edit the fields as follows:
  - **Profile Name:** Descriptive name to identify the application. If your site maintains more than one OnQ application, this is the name that will appear in the **Connection Profiles** drop-down menu when users log in.
  - Server Name/Address: Machine name and static IP address of the SQL Server machine. If there is an instance specified on your server, you must include that instance name in this field.
  - Database Name: Enter the value FQPortal.
  - Login ID: Enter the value fileonquser.
  - **Password:** Supplied by FileOnQ Support in the DBRestore utility or by your database administrator.
- 5. Click OK. Click the Save icon.

🚪 FileOnQ Portal data	base 🔀
Profile Name:	FQPortal
Server Name/Address:	SQLServer2
Database Name:	FQPortal
Login ID:	fileonquser
Password:	******
Reenter password:	******
	UK Cancel



Request License

#### Step 7: Request and Apply a License

Every OnQ application must be licensed. A new OnQ application will function with no license—in "demo mode"—until the database contains 50 records. At that time, you must load a valid license file.

After you request a license file, FileOnQ sends you an encrypted license file as an attachment to an email message. The filename extension for the license file is .lic.

#### **Request a License File**

- 1. From the Windows Start menu, log into the Admin Tool.
- From the Admin Tool, click the profile name that you are requesting a license for.

FileOnQ 6.1 Server Profiles Administ	rator		
<u>F</u> ile <u>P</u> rofile			
	Current Location: C:\Program File	s\FileOnQ\FileOnQ 6.1\Serv	erProfiles.xml
Profile Name Administer the application pointe	d to by this profile Name	Login ID	UseAD
Ledgers SQLServer2	Onq_ledger	fileonquser	
FileOnQ DIANA-5CC50759E\FILEONQDB	1 FileOnQDemo	hileonguser	

Click the Administer Application icon
 Or,
 From the menu at the top of the window, select Profile > Administer Application.

A login window appears.

- 4. Log into the application. The login ID is System. The password is supplied by FileOnQ support.
- 5. Click the **Request License** button on the right side of the window that appears. The **License Request** window appears.

rganization :	MyCompany
pplication/Department Name :	MyDepartment
equestor's Name :	Chris Jones
Mail Address:	cjones@mycompany.com
hone Number:	(877)555-1212 Ext.: 99
omment :	
	-

6. Fill out the fields with your information. Click **Request**. Save the request file with a meaningful name and the extension **.req**.

7. A message tells you that a request file has been created. Send an email message to License@fileonq.com and include the request file as an attachment.

#### Apply the License File

- 1. When you receive the email message that contains the license file, save it to a convenient location.
- 2. Sign into the FileOnQ Administration tool again, select the profile to apply the license to, and then click the **Administer Application** icon.
- 3. Sign in and click the **Load License File** button. The **Select License File** dialog box appears.
- 4. Navigate to the location where you saved the .lic file, select the license file, and then and click **Open**. You should receive a success message.

### Step 8: Install OnQ Desktop Software

All computers that need the Desktop software can install it from the FQDesktopxx.msi file, described on page 8. All of the default settings should be used, which means that the Administration Tools will not be installed. A Windows user with administrative permissions should perform the installations.

If you see an error message that says the ServerProfiles.xml file was not found, you must set the path to this file. From the Admin Tool, select **File > Change Location**, and then specify the network location.

File not found!			
The ServerProfiles or the file does not	file was not four exist. Would y	nd, either the p ou like to enter	ath is incorrect the correct path now?
[	Yes	No	]

### Step 9: Install Peripheral Hardware to Use with FileOnQ

Any computer that has attached hardware—such as a barcode scanner or an electronic signature pad must have those devices installed and configured while the administrator is still logged in.

For installation instructions, see the documentation provided with your hardware devices.

To configure hardware devices, from the main menu, select **Tools > Options > This Workstation**. Use the tabs to find the settings for the particular type of device you want to configure.

Options			
General User This Workstation Queries			
Path Local Wand Portable Wand Signature Pad Batch Transfer			
Cocal Wand			
Com Port: COM2:			
Baud Rate: 9600			
Enable Enhanced Wand			
·			
OK	Cancel		

**NOTE** FileOnQ uses Windows printers, either locally attached or network printers. Although there is no setup inside FileOnQ for any printers, you may have received some configuration information about barcode label printers that will be useful in setting them up to work with FileOnQ.

#### **Step 10: Install Optional Modules**

If your system includes eDocs or WebView, you must set up those optional modules.

#### Install and Configure eDocs

With the bundled eDocs module, users can store electronic files in a SQL database repository. To enable this functionality, you must define at least one storage device and an associated SQL database.

- 1. Start the FileOnQ Administrator program and select the profile for the database to which you want to add the eDocs Repository. Click the 🞦 FileOnQ Administer the application icon.
- 2. Log in to the database using administrator credentials.
- 3. From the window that appears, click eDocs Manager.
- Select SQLServer and then click the Add a new 4 storage device under the selected connector icon.
- 5. Assign a short name and a long name to the New eDocs Storage Device storage device. Click OK. The storage device now Short Name : OnQ\_Docs appears in the list under SQLServer. NOTE Over time, you might add multiple Long Name : OnQ Electronic Document Repository storage devices to an eDocs Repository. Consider an appropriate naming convention so users will be Comment : clear where documents are being stored.
- 6. Select the new storage device and click the Configure Connector icon.
- 7. You are asked whether you want to run the Database Create wizard. Click Yes.

Licensed Connectors :
😹 💽 8 3 5
OnQ_eDocs [OnQ Electronic Documentation Repository]     FileNet1



Add a new storage device under the selected connector

\_ 🗆 🗡

Licensed Connectors :

5 8 3 5

SQLServer 🍣 FileNet1

 Enter the name (and instance if one exists) of the SQL Server that will host this repository. Enter the sa password for this SQL server. Click Next.

🎁 eDocs SQL DB Wizard		
This tool will create a SQ file paths are physically Server is running.	L database for use as a eDocs SQL Storage Device. N on the selected server (Remote or Local) where the	OTE that all host SQL
Server/Instance Address :	DQL2008_X1\Instance2	
Administrator Login :	Sa	
Administrator Password :	*******	
	< Back. Next >	Cancel

9. Complete the fields to define the database and the locations of the data and log files. Choose appropriate starting sizes for the data and log files. These will be set to grow automatically.

**NOTE** The User Login ID is usually the same SQL login that was established for the main FileOnQ database. If this eDocs Repository is on the same SQL Server, it is convenient to use the same SQL login and associated password.

👔 eDocs SQL DB Wizard		
This tool will create a file paths are physica Server is running.	SQL database for use as a eDocs SQL Storage Device. NOTE lly on the selected server (Remote or Local) where the host	that all : SQL
Database Name :	OnQ_eDocs	
Data Logical Name :	OnQ_eDocs_data	
Log Logical Name :	OnQ_eDocs_log	
Device DATA File Path :	\OnQ_eDocs_data.mdf	
Device LOG File Path :	\OnQ_eDocs_log.ldf	
User Login ID :		
User Password :		
DATA File Size (Mb) :	1 LOG File Size (Mb) : 1	
	< Back Create	Cancel
Connected!		//.

10. Supply the full path to the DATA and LOG files for this database, the SQL login and password, and the initial file sizes.

- 11. Click Create. You will see the progress and completion messages in the window. Click Close.
- 12. The eDocs Connector Configurations window will be displayed with the previously chosen parameters. Click **OK**.
- 13. Click the Settings button to go to the FileOnQ database settings window.



14. In the database settings window, make sure the **Document Tab Caption** field contains a value, such as "Documents". Also, we recommend that you select the **Auto-assign Document Barcode** check box. Save and close the FileOnQ Administrator.

Captions	Barcodes Qu	ery Performance	Record Security	Features	
Main Tat	o Caption :	Item Info		Comments Tab :	Comment
Barcode	Caption :	Barcode:		Prompt Text :	Enter Barcode
Containe	er/Box Prefix:	BOX		Container Name :	Box
Docume	nt Tab Caption :	DOCUMENTS		Auto-assign D	ocument Barcode

- 15. You may choose to add document types to the FileOnQ application to organize the stored eDocs by category. An administrator can log in to FileOnQ and, from the Data menu, select Document Collection. The Document Collection Maintenance window appears.
- 16. To add new document types, click **New**. The system will supply consecutive decimal numbers to distinguish between the different types.

Document Types -		
Document Type	Document Type Barco	de
Invoice		.1
Collateral		.2
	New	Delete
		12



### **Technical Support**

#### **Need Assistance?**

Please call (206) 575-3488 or (800) 603-6802 (option 4) for Technical Support.:

Or send questions to: <a href="mailto:support@fileonq.com">support@fileonq.com</a>

#### See us on the web at: www.fileonq.com www.evidenceonq.com